

**DIGITAL
VISION**

COMBOBULATOR

Downloading and Management of Rx and Stock Orders ...and more!


Brian Biggs and Armando Montalban

SOFTWARE ENHANCEMENTS

What does the Combob do?

It's very busy beyond downloading orders:

- ◆ Digital Calculations
- ◆ Job Change Requests
- ◆ Short Orders
- ◆ Statuses
- ◆ Subcontracting
- ◆ Tray Management



SOFTWARE ENHANCEMENTS

Multi-threaded Combobulator software [WSR]

- ◆ Prevents unresponsive digital surfacing servers from impacting other operations
- ◆ Improves performance by reducing wait times
- ◆ Multiple tasks performed simultaneously



WEB MIGRATION

- ◆ DVI Enterprise
- ◆ Cloud based services
- ◆ More secure
- ◆ Robust



RECOMMENDED QUEUES



Standard features that should be implemented

- ◆ Consolidated Subcontracting
- ◆ Lens and Frame Short Orders
- ◆ Labels for Supplied Frame Jobs
- ◆ Auto-reprocess Frame Tracing
- ◆ Digital Surfacing Calculation Results

| Name | Count | Age | Status |
|------------------|-------|-----------|--------|
| Customer Service | 11 | 74:11:25 | |
| Second Pair | 0 | | |
| Digital Calc | 0 | | |
| Failed Calc | 0 | | |
| STOCK JOBS | 1 | 6:11:56 | |
| Review | 27 | 27:14:25 | |
| FTC Wait | 16 | 44:14:47 | |
| FTC Auto | 0 | | % 0 |
| Frame Order | 0 | | |
| Frames Ordered | 30 | 48:11:33 | |
| Frames Received | 0 | | |
| Subcon | 6 | 27:14:55 | |
| Subcon Sent | 228 | 45:08:09 | |
| Subcon Fail | 0 | | |
| Lens order | 46 | 31:11:54 | |
| Lens on Order | 159 | 255:08:54 | |
| Lens Rcvd | 0 | | % 0 |
| FINISHED LENSES | 2 | 27:09:42 | |
| SEMI FINISHED | 2 | 6:11:15 | |
| Uncategorized | 0 | | |
| Promoted Edits | 0 | | |
| Rmt Rx Modified | 0 | | |
| Edits | 40 | 27:12:13 | |

RECOMMENDED QUEUES

◆ Consolidated Subcontracting

All vendors in one bucket when possible.

Setting it to Auto-Release will automate subcontracting

◆ Frame and Lens Short Orders

◆ Labels for Supplied Frame Jobs

| Name | Count | Age | Status |
|-------------------|-------|-----------|--------|
| Customer Order | 0 | | |
| Subcon | 6 | 27:14:26 | |
| Subcon Sent | 228 | 45:07:40 | |
| Subcon Fail | 0 | | |
| Rev Order | 46 | 31:11:54 | |
| FTC Wait | 16 | 44:14:47 | |
| FTC Auto | 0 | | %0 |
| Frame Order | 0 | | |
| Frame Order | 0 | | |
| Frames Ordered | 30 | 48:11:33 | |
| Frames Received | 0 | | |
| Subcon Fail | 0 | 6:07:15 | |
| Lens order | 46 | 31:11:54 | |
| Lens on Order | 159 | 255:08:54 | |
| FINISHED | 0 | | |
| SEMI FINISHED | 2 | 6:11:15 | |
| Uncategorized | 0 | | |
| Promoted Received | 0 | | |
| Supl Frame Label | 0 | | |
| Supplied Lenses | 0 | | |

RECOMMENDED QUEUES

◆ Auto-reprocess Frame Tracing

- Saves paper and steps

| Name | Count | Age | Status |
|------------------|-------|----------|--------|
| Customer Service | 11 | 74:11:25 | |

| | | | |
|-------------|----|----------|-----|
| Review | 27 | 27:14:20 | |
| FTC Wait | 16 | 44:14:47 | |
| FTC Auto | 0 | | % 0 |
| Frame Order | 0 | | |

| | | | |
|-----------------|-----|----------|--|
| Frame Order | 0 | | |
| Frames Ordered | 30 | 48:11:33 | |
| Frames Received | 0 | | |
| Subcon | 6 | 27:14:55 | |
| Subcon Sent | 228 | 45:08:09 | |
| Subcon Fail | 0 | | |

| | | | |
|--------------|---|--|--|
| Digital Calc | 0 | | |
| Failed Calc | 0 | | |

| | | | |
|------------------|----|----------|--|
| FINISHED - BENCH | 1 | 6:12:11 | |
| SEMI FINISHED | 2 | 6:11:15 | |
| Uncategorized | 0 | | |
| Promoted Edits | 0 | | |
| Rmt Rx Modified | 0 | | |
| Edits | 40 | 27:12:13 | |

◆ Digital Surfacing Calculation Results

- Corrals jobs that can't be started yet
- Front-ends calculation errors

NEW SOFTWARE TOOLS



Recheck Queue Logic Against Jobs

New menu option to re-sort work on demand

- ◆ Jobs with new statuses may not be in currently appropriate queue
- ◆ Eliminates need to save a “change” to force re-sort
- ◆ Different from “Reprocess Rx’s”
 - Recheck does not recalculate job in Rx program
- ◆ Commonly used after receiving lens orders, prior to creating new orders

| | | | |
|-----------------|-----|----------|-----|
| ftc hold NEW | 16 | 38:01:49 | |
| Auto FTC | 0 | | % 0 |
| Frame Order | 0 | | |
| Subcon | 4 | 21:01:57 | |
| Subcon Sent | 228 | 38:19:11 | |
| Subcon Fail | 0 | | |
| Lens order | 46 | 24:22:56 | |
| Lens on Order | | | |
| Lens Rcvd no Fr | | | |
| Lens Rec New Ac | | | |
| Lens Rcvd | | | |
| FINISHED LENSES | | | |
| SEMI FINISHED | | | |
| Uncategorized | | | |
| Promoted Edits | | | |
| Rmt Rx Modified | | | |
| Edits | 40 | 20:23:15 | |

- Process to Specified Trays
- Process All
- Process Some
- Manual Review
- Receive from Subcontractor, assign Cost and Tray#
- Order Frames
- Order Lenses
- Reprocess Rx's
- Recheck Queue Logic against Jobs

NEW SOFTWARE TOOLS

Print Label / PDF option^[WSR]

New menu option to print custom form

- ◆ Replaces traditional workticket when releasing job from queue
- ◆ Can have unique setup from queue to queue
- ◆ Label version uses non-standard Customized Workticket form
 - Label dimension definable for custom media (tags, stickers, different paper size, etc.)
- ◆ PDF version currently used with automated storage and retrieval systems (ASRS)

The screenshot shows a configuration dialog box with the following fields and options:

- Service Code:
- Stay in Combobulator
- Max #Orders Releasable:
- modified 04/29/24 by @@
- Printing Option:
- Wtk Label:
- Frame Label:
- Stock Order Queue
- Hold Queue
- Subcontract Queue
- Auto FTC Queue
- Pinnable
- Assign FTC Bin:
- Bin Range:
- OK button

NEW SOFTWARE TOOLS



New Data Types!

- ◆ Hundreds of available data type options to sort work
- ◆ New fields available:
 - Stock Category
 - Frame Trace Source (Pattern vs. Frame)
 - Frame Division
 - Frame Comment
 - Frame UPC
 - Tint Description
 - Ultimate Vendor
 - Subcontractor Lab Status
 - “ASRS” options (Automatic Storage and Retrieval)

NEW SOFTWARE TOOLS

Second Pair Detection^[WSR]

- ◆ Option in DVI settings
 - Used in tandem with duplicate order settings
- ◆ Activated when frame, lens style, material or colors differ



| | | |
|--------------------------------|--------------|--------------------|
| AR Transfer Version | D | AR Transfer vers |
| Mega Transfer File | WS24MEGA.XML | Mega Transfer fil |
| Mega Transfer Version | E | Mega Transfer ve |
| HIPAA Mega Transfer Option | | Number of charac |
| Include Breakage Detail | Y | Y=Show breakag |
| Breakages for Brksum | 3 | Jobs with fewer th |
| Rx Duplicates: Rx Number | Y | Y=Use Rx Numbe |
| Rx Duplicates: Patient | N | Y=Use Patient in |
| Rx Duplicates: Soundex Patient | Y | Y=Use Soundex p |
| Rx Duplicates: Account | Y | Y=Use Account in |
| Second Pair Detection | Y | Y=Enable second |
| Rx Duplicate Days | 60 | Days to store Rx |
| Print Reports | N | Y=Print reports af |
| Email Reports | Y | Y=Email reports a |
| Rx Screen File | S | .Jobs in rx screen |

NEW SOFTWARE TOOLS

Second Pair Detection

- ◆ Combobulator queue to capture potential second pairs
 - “Second Pair” = TRUE
 - Job no longer starts life as edit problem
 - Second Pair orders now sorted into queue where a specialist can approve
 - First pair can be in process or shipped within duplicate date range

| Name | Count | Age | Status |
|------------------|-------|----------|--------|
| Customer Service | 11 | 74:11:25 | |
| Second Pair | 0 | | |
| Digital Lab | 0 | | |
| Failed Calc | 0 | | |
| STOCK JOBS | | 6:11:56 | |
| Review | 27 | 27:14:25 | |



Define Queue

| Queue Name | Description | ID |
|-------------|---------------------------|----|
| Second Pair | Potentially a second pair | 8 |

Job Inclusion Criteria

| | Data Type | Operator | Value(s) | Eye(s) |
|---|-------------|----------|----------|--------|
| 1 | Second Pair | = | TRUE | |
| 2 | | | | |
| 3 | | | | |

Print

NEW SOFTWARE TOOLS

Re-Combobulating from List File

- ◆ Useful for when many jobs are accidentally released, especially if worktickets aren't physically present
- ◆ Previously only manual reprocessing or typing/scanning trays
- ◆ Command line utility only
 - Work with DVI
- ◆ Consider preventative measures:
 - Hold Queue
 - Limit amount releasable at once



Max #Orders Releasable
modified 04/29/24 by @@

Printir

Lat

CU

Wtkk

**DIGITAL
VISION**

THANK YOU

Contact Digital Vision:

(503) 231-6606 | info@thedvi.com